- CHAPTER 2 - GEMDOS

Overview

GEMDOS contains functions which comprise the highest level of **TOS**. In many cases, **GEMDOS** devolves into **BIOS** calls which handle lower level device access. **GEMDOS** is responsible for file, device, process, and high-level input/output management. The current revision number of **GEMDOS** is obtained by calling **Sversion**(). You should note that the **GEMDOS** version number is independent of the **TOS** version number and you should not count on any particular version of **GEMDOS** being present based on the **TOS** version present.

Much of **GEMDOS** closely resembles its CPM 68k and MS-DOS heritage. In fact, the file system and function calls are mostly compatible with MS-DOS. MS-DOS format floppy disks are readable by an Atari computer and vice-versa.

For the creation of **MultiTOS**, **GEMDOS** was merged with the **MiNT** operating environment which derives many of its calls from the UNIX operating system.

The TOS File System

GEMDOS is responsible for interaction between applications and file-based devices. Floppy and hard disk drives as well as CD-ROM, WORM, and Magneto-Optical drives are all accessed using **GEMDOS** calls.

Prior to the advent of **MultiTOS**, Atari programmers were limited to the **TOS** file system for file storage and manipulation. With the introduction of **MultiTOS**, it is now possible for developers to create custom file systems so that almost any conceivable disk format becomes accessible.

As a default, **MultiTOS** will manage files between the **TOS** file system and alternative file systems to maintain backward compatibility. Applications which wish to support extra file system features may do so. The **Pdomain()** call may be used to instruct **MultiTOS** to stop performing translations on filenames, etc. Other calls such as **Dpathconf()** can be used to determine the requirements of a particular file system.

The explanation of the file system contained herein will limit itself to the **TOS** file system.

Drive Identifiers

Each drive connected to an Atari system is given a unique alphabetic identifier which is used to identify it. Drive 'A' is reserved for the first available floppy disk drive (usually internal) and drive 'B' for the second floppy disk drive. If only one floppy drive exists, two letters will still be reserved and **GEMDOS** will treat drive 'B' as a pseudo-drive and request disk swaps as necessary. This feature is automatically handled by **GEMDOS** and is transparent to the application.

Drives 'C' through 'P' are available for use by hard disk drives. One letter is assigned per hard drive partition so a multiple-partition drive will be assigned multiple letters. **MultiTOS** extends drive letter assignments to 'Z' drive. Drive 'U' is a special drive reserved for **MultiTOS** and is unavailable for assignment.

The amount of free storage space remaining on a drive along with a drive's basic configuration can be determined using the **Dfree()** call.

GEMDOS Filenames

Under **GEMDOS**, each file located on a device is given a filename upon its creation which serves to provide identification for the file. The filename has two parts consisting of a name from one to eight characters long and an optional file extension of up to three characters long. If a file extension exists, the two components are separated by a period. The extension should serve to identify the format of the data whereas the name itself should identify the data itself.

Filenames may be changed after creation with the function **Frename**(); however, under no circumstances may two files with the same filename reside in the same directory.

All **GEMDOS** functions ignore the alphabetic case of file and pathnames. The following characters are legal filename characters:

Legal GEMDOS Filename Characters
A-Z, a-z, 0-9
! @ # \$ % ^ & ()
+ - = ~ ` ; ` " ,
< > [] () _

GEMDOS Directories

To further organize data, **GEMDOS** provides file directories (or folders). Each drive may contain any number of directories which, in turn, may contain files and additional directories. This organization creates a tree-like structure of files and folders. A file's location in this tree is called the path.

Directory names follow the same format as **GEMDOS** filenames with a maximum filename length of 8 characters and an optional 3 character extension. The first directory of a disk which contains all subdirectories and files is called the root directory.

The **Dcreate()** and **Ddelete()** system calls are used to create and delete subdirectories.

Two special, system-created subdirectories are present in some directories. A subdirectory with the name '..' (two periods) refers to the parent of the current directory. The '..' subdirectory is present in every subdirectory.

A subdirectory with the name '.' refers to the current directory. There is a '.' subdirectory in every directory.

GEMDOS Path Specifications

To access a file, a complete path specification must be composed of the drive letter, directory name(s), and filename. A file named 'TEST.PRG' located in the 'SYSTEM' directory on drive 'C' would have a path specification like the following:

C:\SYSTEM\TEST.PRG

The drive letter is the first character followed by a colon. Each directory and subdirectory is surrounded by backslashes. If 'TEST.PRG' were located in the root directory of 'C' the path specification would be:

C:\TEST.PRG

The drive letter and colon may be omitted causing **GEMDOS** to reference the default drive as follows:

\TEST.PRG

A filename by itself will be treated as the file in the default directory and drive. The current **GEMDOS** directory and drive may be found with the functions **Dgetpath()** and **Dgetdrv()** respectively. They may be changed with the functions **Dsetpath()** and **Dsetdrv()**.

Wildcards

The **GEMDOS** functions **Fsfirst()** and **Fsnext()** are used together to enumerate files of a given path specification. These two functions allow the use of wildcard characters to expand their search parameters.

The '?' character is used to represent exactly one unknown character. The '*' character is used to represent any number of unknown characters. The following table gives some examples of the uses of these characters.

Filename	Found	Not Found
* *	All files	None
*.GEM	TEST.GEM	TEST.G
	ATARI.GEM	ATARI.IMG
A?ARI.?	ATARI.O	ADARI.IMG
	ADARI.C	ATARI.GEM
ATARI.???	ATARI.GEM	ATARI.O
	ATARI.IMG	ATARI.C

Disk Transfer Address (DTA)

When using **Fsfirst()** and **Fsnext()** to build a list of files, **TOS** uses the Disk Transfer Address (DTA) to store information about each file found. The format for the DTA structure is as follows:

```
typedef struct
{
  BYTE    d_reserved[21];    /* Reserved - Do Not Change */
  BYTE    d_attrib;    /* GEMDOS File Attributes */
  UWORD    d_time;    /* GEMDOS Time */
  UWORD    d_date;    /* GEMDOS Date */
  LONG    d_length;    /* File Length */
  char    d_fname[14];    /* Filename */
} DTA;
```

When a process is started, its DTA is located at a point where it could overlay potentially important system structures. To avoid overwriting memory a process wishing to use **Fsfirst()** and **Fsnext()** should allocate space for a new DTA and use **Fsetdta()** to instruct the OS to use it. The original location of the DTA should be saved first, however. Its location can be found with the call **Fgetdta()**. At the completion of the operation the old address should be replaced with **Fsetdta()**.

File Attributes

Every **TOS** file contains several attributes which define it more specifically. File attributes are specified when a file is created with **Fcreate()** and can be altered later with **Fattrib()**.

The 'read-only' attribute bit is set to prevent modification of a file. This bit should be set at the user's discretion and not cleared unless the user explicitly requests it.

If the 'hidden' attribute is set, the file will not be listed by the desktop or file selector. These files may still be accessed in a normal manner but will not be present in an **Fsfirst()** or **Fsnext()** search unless the correct **Fsfirst()** bits are present.

The 'system' attribute is unused by **TOS** but remains for MS-DOS compatibility.

The 'volume label' attribute should be present on a maximum of one file per drive. The file which has it set should be in the root directory and have a length of 0. The filename indicates the volume name of the drive.

The 'archive' attribute is a special bit managed by **TOS** which indicates whether a file has been written to since it was last backed up. Any time a **Fcreate()** call creates a file or **Fwrite()** is used on a file, the Archive bit is set. This enables file backup applications to know which files have been modified since the last backup. They are responsible for clearing this bit when backing up the file.

File Time/Date Stamp

When a file is first created a special field in its directory entry is updated to contain the date and time of creation. **Fdatime()** can be used to access or modify this information as necessary.

File Maintenance

New files should be created with **Fcreate()**. When a file is successfully created a positive file handle is returned by the call. That handle is what is used to identify the file for all future operations until the file is closed. After a file is closed its handle is invalidated.

Files which are already in existence should be opened with **Fopen**(). As with **Fcreate**(), this call returns a positive file handle upon success which is used in all subsequent **GEMDOS** calls to reference the file.

Each process is allocated an OS dependent number of file handles. If an application attempts to open more files than this limit allows, the open or create call will fail with an appropriate error code. File handles may be returned to the system by closing the open file with **Fclose()**.

Fopen() may be used in read, write, or read/write mode. In read mode, **Fread**() may be used to access existing file contents. In write mode, any original information in the file is not cleared but the data may be overwritten with **Fwrite**(). In read/write mode, either call may be used interchangeably.

Every file has an associated file position pointer. This pointer is used to determine the location for the next read or write operation. This pointer is expressed as a positive offset from the beginning of the file (position 0) which is set upon first creating or opening a file. The pointer may be read or modified with the function Fseek().

Existing files may be deleted with the **GEMDOS** call **Fdelete()**.

File/Record Locking

File and record locking allow portions or all of a file to be locked against access from another computer over a network or another process in the same system.

All versions of **TOS** have the ability to support file and record locking but not all have the feature installed. If the '_FLK' cookie is present in the system cookie jar then the **Flock()** call is present. This call is used to create locks on individual sections (usually records) in a file.

Locking a file in use, when possible, is recommended to prevent other processes from modifying the file at the same time.

Special File Handles

Several special file handles are available for access through the standard **Fopen()/Fread()/Fwrite()** calls. They are as follows:

Name	Handle	Filename	Device
GSH_BIOSCON	0xFFFF	CON:	Console (screen). Special characters such as the carriage return, etc. are interpreted.
GSH_BIOSAUX	0xFFFE	AUX:	Modem (serial port). This is the ST- compatible port for machines with more than one.
GSH_BIOSPRN	0xFFFD	PRN:	Printer (attached to the Centronics Parallel port).
GSH_BIOSMIDIIN	0xFFFC		Midi In
GSH_BIOSMIDIOUT	0xFFFB		Midi Out

GSH_CONIN	0x00	1	Standard Input (usually directed to GSH_BIOSCON)
GSH_CONOUT	0x01	I	Standard Output (usually directed to GSH_BIOSCON)
GSH_AUX	0x02	_	Auxillary (usually directed to GSH_BIOSAUX)
GSH_PRN	0x03	_	Printer (usually directed to GSH_BIOSPRN)
None	0x04		Unused
None	0x05		Unused
None	0x06 and up	User-Specified	User Process File Handles

These files may be treated like any other **GEMDOS** files for input/output and locking. Access to these devices is also provided with **GEMDOS** character calls (see later in this chapter).

File Redirection

Input and output to a file may be redirected to an alternate file handle. For instance you may redirect the console output of a **TOS** process to the printer.

File redirection is handled by the use of the **Fforce**() call. Generally you will want to make a copy of the file handle with **Fdup**() prior to redirecting the file so that it may be restored to normal operation when complete.

Memory Management

Atari systems support two kinds of memory. Standard RAM (sometimes referred to as 'ST RAM') is general purpose RAM that can be used for any purpose including video and DMA. Current Atari architecture limits the amount of standard RAM a system may have to 14MB.

Alternative RAM (sometimes referred to as 'TT RAM') can be accessed faster than standard RAM but is not suitable for video memory or DMA transfers.

The **Malloc()** and **Mxalloc()** calls allocate memory blocks from the system heap. **Malloc()** chooses the type of memory it allocates based on fields in the program header (see later in this chapter). **Mxalloc()** allows the application to choose the memory type at run-time.

MultiTOS uses memory protection to prevent an errant process from damaging another. It is possible with **Mxalloc**() to dynamically set the protection level of an allocated block.

Memory allocated with either **Malloc()** or **Mxalloc()** may be returned to the system with **Mfree()**. Memory allocated by a process is automatically freed when the process calls **Pterm()**.

GEMDOS Processes

The **GEMDOS** call **Pexec()** is responsible for launching executable files. The process which calls **Pexec()** is called the parent and the file launched becomes the child. Each process may

have more than one child process. Depending on the mode used with Pexec(), the child may share data and address space and/or run concurrently (under MultiTOS) with the parent. GEMDOS executable files (GEM and TOS applications or desk accessories) contain the following file header:

Name	Offset	Contents
PRG magic	0x00	This WORD contains the magic value
T KO_magic	0,000	(0x601A).
PRG tsize	0x02	This LONG contains the size of the TEXT
		segment in bytes.
PRG_dsize	0x06	This LONG contains the size of the
		DATA segment in bytes.
PRG_bsize	0x0A	This LONG contains the size of the BSS
		segment in bytes.
PRG_ssize	0x0E	This LONG contains the size of the
		symbol table in bytes.
PRG_res1	0x12	This LONG is unused and is currently
		reserved.
PRGFLAGS	0x16	This LONG contains flags which define
		certain process characteristics (as
		defined below).
ABSFLAG	0x1A	This WORD flag should be non-zero to
		indicate that the program has no fixups or
		0 to indicate it does.
		Since some versions of TOS handle files
		with this value being non-zero incorrectly,
		it is better to represent a program having
		no fixups with 0 here and placing a 0
	0.40	longword as the fixup offset.
Text Segment	0x1C	This area contains the program's TEXT
		segment. A process is started by
		JMP'ing to BYTE 0 of this segment with
		the address of your processes basepage at 4(sp).
Data Segment	PRG tsize+	This area contains the program's DATA
Data Segment	0x1C	segment (if one exists).
Symbol Segment	PRG_tsize +	This area contains the program's symbol
	PRG dsize+	table (if there is one). The symbol table
	0x1C	area is used differently by different
		compiler vendors. Consult them for the
		format.
Fixup Offset	PRG_tsize+	This LONG indicates the first location in
	PRG_dsize+	the executable (as an offset from the
	PRG_ssize+	beginning) containing a longword
	0x1C	needing a fixup. A 0 means there are no
		fixups.

Fixup Information	PRG_tsize + PRG_dsize + PRG_ssize + 0x20	This area contains a stream of BYTE s containing fixup information. Each byte has a significance as follows:	
		Value 0 1 2-254 (even)	Meaning End of list. Advance 254 bytes. Advance this many bytes and fixup the longword there.

PRGFLAGS is a bit field defined as follows:

Definition	Bit(s)	Meaning
PF_FASTLOAD	0	If set, clear only the BSS area on program
		load, otherwise clear the entire heap.
PF_TTRAMLOAD	1	If set, the program may be loaded into
		alternative RAM, otherwise it must be
		loaded into standard RAM.
PF_TTRAMMEM	2	If set, the program's Malloc() requests may
		be satisfied from alternative RAM, otherwise
		they must be satisfied from standard RAM.
_	3	Currently unused.
See left.	4 & 5	If these bits are set to 0 (PF_PRIVATE), the
		processes' entire memory space will be
		considered private (when memory
		protection is enabled).
		If these bits are set to 1 (PF_GLOBAL), the
		processes' entire memory space will be
		readable and writable by any process (i.e.
		global).
		If the see hite are set to O
		If these bits are set to 2
		(PF_SUPERVISOR), the processes' entire
		memory space will only be readable and
		writable by itself and any other process in supervisor mode.
		Supervisor mode.
		If these bits are set to 3 (PF_READABLE),
		the processes' entire memory space will be
		readable by any application but only writable
		by itself.
_	6-15	Currently unused.

When a process is started by **GEMDOS**, it allocates all remaining memory, loads the process into that memory, and JMP's to the first byte of the application's TEXT segment with the address of the program's basepage at 4(sp). An application should use the basepage information to decide upon the amount of memory it actually needs and **Mshrink()** to return the rest to the system. The exception to this is that desk accessories are only given as much space as they need (as indicated by their program header) and their stack space is pre-assigned.

The following code illustrates the proper way to release system memory and allocate your stack (most 'C' startup routines do this for you):

```
stacksize
               $2000
                               ; 8K
                .text
_start:
       move.1 $18(a0),a1 ; BSS Base address adda.1 $1C(a0),a1 ; Add BSS size
       adda.l #stacksize,al
                                   ; Add stack size
                               ; Move your stack pointer to
       move.l al,sp
                               ; your new stack.
       suba.l basepage,a1
                              ; TPA size
       move.l a1,-(sp)
       move.l basepage,-(sp)
       clr.w
               -(sp)
       move.w #$4a,-(sp)
                              ; Mshrink()
       trap
               #1
       lea
               12(sp),sp
                              ; Fix up stack
                               ; and fall through to main
_main:
      . . .
                .bss
               ds.1
                       1
basepage:
                .end
```

The **GEMDOS BASEPAGE** structure has the following members:

Name	Offset	Meaning
p_lowtpa	0x00	This LONG contains a pointer to the Transient
		Program Area (TPA).
p_hitpa	0x04	This LONG contains a pointer to the top of the
		TPA + 1.
p_tbase	0x08	This LONG contains a pointer to the base of
		the text segment
p_tlen	0x0C	This LONG contains the length of the text
		segment.
p_dbase	0x10	This LONG contains a pointer to the base of
		the data segment.
p_dlen	0x14	This LONG contains the length of the data
		segment.
p_bbase	0x18	This LONG contains a pointer to the base of
		the BSS segment.
p_blen	0x1C	This LONG contains the length of the BSS
		segment.
p_dta	0x20	This LONG contains a pointer to the
		processes' DTA.

p_parent	0x24	This LONG contains a pointer to the
		processes' parent's basepage.
p_reserved	0x28	This LONG is currently unused and is
		reserved.
p_env	0x2C	This LONG contains a pointer to the
		processes' environment string.
p_undef	0x30	This area contains 80 unused, reserved bytes.
p_cmdlin	0x80	This area contains a copy of the 128 byte
		command line image.

Processes terminate themselves with either **Pterm0**(), **Pterm(**), or **Ptermres**(). **Ptermres**() allows a segment of a file to remain behind in memory after the file itself terminates (this is mainly useful for TSR utilities).

The Atari Extended Argument Specification

When a process calls **Pexec()** to launch a child, the child may receive a command line up to 125 characters in length. The command line does not normally contain information about the process itself (what goes in argv[0] in 'C'). The Atari Extended Argument Specification (ARGV) allows command lines of any length and correctly passes the child the command that started it. The ARGV specification works by passing the command tail in the child's environment rather than in the command line buffer.

Both the parent and child have responsibilities when wanting to correctly handle the ARGV specification. If a process wishes to launch a child with a command line of greater than 125 characters it should follow these steps:

- Allocate a block of memory large enough to hold the existing environment, the string 'ARGV=' and its terminating NULL, a string containing the complete path and filename of the child process and its terminating NULL, and a string containing the child's command line arguments and its terminating NULL.
- 2. Next, copy these elements into the reserved block in the order given above.
- 3. Finally, call **Pexec()** with this environment string and a command line containing a length byte of 127 and the first 125 characters of the command line with a terminating **NULL**.

For a child to correctly establish that a parent process is using ARGV it should check for the length byte of 127 and the ARGV variable. Some parents may assign a value to ARGV (found between the 'ARGV=' and the terminating **NULL** byte). It should be skipped over and ignored. If a child detects that its parent is using ARGV, it then has the responsibility of breaking down the environment into its components to properly obtain its command line elements.

It should be noted that many compilers include ARGV parsing in their basic startup stubs. In addition, applications running under **MultiTOS** should use the **AES** call **shel_write()** as it automatically creates an ARGV environment string.

GEMDOS Vectors

GEMDOS reserves eight system interrupt vectors (of which only three are used) for various system housekeeping. The **BIOS** function **Setexc()** should be used to redirect these vectors when necessary. The **GEMDOS** vectors are as follows:

Name	Setexc() Vector Number	Usage
VEC_TIMER	0x0100	Timer Tick Vector: This vector is jumped through 50 times per second to maintain the time-of-day clock and accomplish other system housekeeping. A process intercepting this vector does not have to preserve any registers but should jump through the old vector when completed. Heavy use of this vector can severly affect system performance. Return from this handler with RTS.
VEC_CRITICALERR	0x0101	Critical Error Handler: This vector is used by the BIOS to service critical alerts (an Rwabs() disk error or media change request). When called, the WORD at 4(sp) is a GEMDOS error number. On return, D0.L should contain 0x0001000 to retry the operation, 0 to ignore the error, or 0xFFFFFFxx to return an error code (xx). D3-D7 and A3-A6 must be preserved by the handler. Return from this handler with RTS.
VEC_PROCTERM	0x0102	Process Terminate Vector: This vector is called just prior to the termination of a process ended with CTRL-C. Return from this handler with RTS.
_	0x103-0x0107	Currently unused.

MINT

MiNT is Now TOS (MiNT) is the extension to GEMDOS that allows GEMDOS to multitask under MultiTOS. MiNT also provides memory protection (on a 68030 or higher) to protect an errant process from disturbing another.

Processes

MiNT assigns each process a process identifier and a process priority value. The identifier is used to distinguish the process from others in the multitasking environment. **Pgetpid()** is used to obtain the **MiNT** ID of the process and **Pgetppid()** can be used to obtain the ID of the processes' parent.

MiNT also supports networking file systems that support the concept of user and process group control. The **Pgetpgrp()**, **Psetpgrp()**, **Pgetuid()**, **Psetuid()**, **Pgeteuid()**, and **Pseteuid()** get and set the process, user, and effective user ID for a process.

MiNT has complete control over the amount of time allocated to individual processes. It is possible, however, to set a process 'delta' value with **Pnice()** or **Prenice()** which will be used by **MiNT** to decide the amount of processor time a process will get per timeslice. **Syield()** can be used to surrender the remaining portion of a timeslice.

Information about a processes' resource usage can be obtained by calling **Prusage**(). These values can be modified with **Psetlimit**(). System configuration capabilities may be obtained with **Sysconf**().

Each process can have a user-defined longword value assigned to itself with **Pusrval**().

The functions **Pwait()**, **Pwait3()**, and **Pwaitpid()** attempt to determine the exit codes of stopped child processes.

Threads

It is possible under **MiNT** to split a single process into 'threads'. These threads continue execution independently as unique processes. The **Pfork()** and **Pvfork()** calls are used to split a process into threads.

The original process that calls **Pfork**() or **Pvfork**() is considered the parent and the newly created process is considered the child.

Child processes created with **Pfork**() share the TEXT segment of the parent, however they are given a copy of the DATA and BSS segments. Both the parent and child execute concurrently.

Child processes created with **Pvfork**() share the entire program code and data space including the processor stack. The parent process is suspended until the child exits or calls **Pexec**()'s mode 200.

Child processes started with either call may make **GEM** calls but a child process started with **Pfork()** must call **appl_init()** to force **GEM** to uniquely recognize it as an independent process. This is not necessary with **Pvfork()** because all program variables are shared.

The following is a simple example of using a thread in a **GEM** application:

```
Pterm( 0 );
}

/* Parent returns and continues normal execution. */
}
```

File System Extensions

MiNT provides several new file and directory manipulation functions that work with **TOS** and other loadable file systems. The **Fcntl()** function performs a large number of file-based tasks many of which apply to special files like terminal emulators and 'U:\' files. **Fxattr()** is used to obtain a file's extended attributes. Some extended attributes are not relevant to the **TOS** file system and will not return meaningful values (see the *Function Reference* for details).

Fgetchar() and **Fputchar()** can be used to get and put single characters to a file. **Finstat()** and **Foutstat()** are used to determine the input or output status of a file. **Fselect()** is used to select from a group of file handles those ready to be read from or written to (often used for pipes).

Flink(), **Fsymlink()**, and **Freadlink()** are used to create hard and symbolic links to another file. Links are not supported by all file systems (see the entries for these functions for more details).

Some file systems may support the concept of file ownership and access permissions (**TOS** does not). The **Fchown()** and **Fchmod()** calls are used to adjust the ownership flags and access permissions of a file. **Pumask()** can be used to set the minimum access permissions assigned to each subsequently created file.

Fmidipipe() is used to redirect the file handles used for MIDI input and output.

MiNT provides four new functions for directory enumeration (they provide similar functionality to **Fsfirst()** and **Fsnext()** with a slightly easier interface). **Dopendir()** is used to open a directory for enumeration. **Dreaddir()** steps through each entry in a directory. **Drewinddir()** resets the file pointer to the beginning of the directory. **Dclosedir()** closes a directory.

Dlock() allows disk-formatters and other utilities which require exclusive access to a drive the ability to lock a physical device from other processes.

Dgetcwd() allows a process to obtain the current **GEMDOS** working directory for any process in the system (including itself).

Dcntl() performs device and file-system specific operations (consult the *Function Reference* for more details).

Pseudo Drives

MiNT creates a pseudo drive 'U:' which provides access to device drivers, processes, and other system resources. In addition to creating a directory on drive U: for each system drive, **MiNT** may create any of the following directories at the ROOT of the drive:

\DEV	Loaded devices	
\PIPE	System pipes	
\PROC	System processes	
\SHM	Shared memory blocks	

Drive directories on 'U:' act as if they were accessed by their own drive letter. Folder 'U:\C\' contains the same files and folders as 'C:\'.

The 'U:\PROC' Directory

Each system process has a file entry in the 'U:\PROC' directory. The filename given a process in this directory is the basename for the file (without extension) with an extension consisting of the **MiNT** process identifier. The MINIWIN.PRG application might have an entry named 'MINIWIN.003'.

The file size listed corresponds to the amount of memory the process is using. The time and date stamp contains the length of time the process has been executing as if it were started on Jan. 1st, 1980 at midnight. The file attribute bits tell special information about a process as follows:

	Attribute	
Name	Byte	Meaning
PROC_RUN	0x00	The process is currently running.
PROC_READY	0x01	The process is ready to run.
PROC_TSR	0x02	The process is a TSR.
PROC_WAITEVENT	0x20	The process is waiting for an event.
PROC_WAITIO	0x21	The process is waiting for I/O.
PROC_EXITED	0x22	The process has been exited but not
		yet released.
PROC_STOPPED	0x24	The process was stopped by a
		signal.

Loadable Devices

MiNT contains a number of built-in devices and also supports loadable device drivers. Current versions of **MiNT** may contain any of the following devices:

Device	
Filename	Device
CENTR	Centronics Parallel Port
MODEM1	Modem Port 1
MODEM2	Modem Port 2
SERIAL1	Serial Port 1
SERIAL2	Serial Port 2
MIDI	MIDI ports
PRN	PRN: device (usually the Centronics Parallel Port)
AUX	AUX: device (usually the RS232 Port)
CON	Current Terminal
TTY	Current Terminal (same as CON)
STDIN	Current File Handle 0 (standard input)
STDOUT	Current File Handle 1 (standard output)
STDERR	Current File Handle 2 (standard error)
CONSOLE	Physical Console (keyboard/screen)

THE ATARI COMPENDIUM

MOUSE	Mouse (system use only)
NULL	NULL device
AES_BIOS	AES BIOS Device (system use only)
AES_MT	AES Multitasking Device (system use only)

Each of these devices is represented by a filename (as shown in the table above) in the 'U:\DEV\' directory. Using standard **GEMDOS** calls (ex: **Fread**() and **Fwrite**()) on these files yields the same results as accessing the device directly. New devices, including those directly accessible by the **BIOS**, may be added to the system with the **Dcntl**() call using a parameter of **DEV_INSTALL**, **DEV_NEWBIOS**, or **DEV_NEWTTY**. See the **Dcntl**() call for details.

MiNT versions 1.08 and above will automatically load device drivers with an extension of 'XDD' found in the root or '\MULTITOS' directory. 'XDD' files are special device driver executables which are responsible for installing one (or more) new devices. **MiNT** will load the file and JSR to the first instruction in the TEXT segment (no parameters are passed). The device driver executable should not attempt to **Mshrink()** or create a stack (one has already been created).

The '.XDD' may then either install its device itself with **Dcntl**() and return **DEV_SELFINST** (1L) in register D0 or return a pointer to a **DEVDRV** structure to have the **MiNT** kernel install it (the 'U:\DEV\' filename will be the same as the first eight characters of the '.XDD' file). If for some reason, the device can not be initialized, 0L should be returned in D0.

When creating a new **MiNT** device with **Dcntl**(**DEV_INSTALL**, *devname*, & *dev_descr*) the structure **dev_descr** contains a pointer to your **DEVDRV** structure defined as follows:

```
typedef struct devdrv
{
    LONG (*open)( FILEPTR *f );
    LONG (*write)( FILEPTR *f, char *buf, LONG bytes );
    LONG (*read)( FILEPTR *f, char *buf, LONG bytes );
    LONG (*lseek)( FILEPTR *f, LONG where, LONG whence );
    LONG (*ioctl)( FILEPTR *f, WORD mode, VOIDP buf );
    LONG (*datime)( FILEPTR *f, WORD *timeptr, WORD rwflag );
    LONG (*close)( FILEPTR *f, WORD pid );
    LONG (*select)( FILEPTR *f, LONG proc, WORD mode );
    LONG (*unselect)( FILEPTR *f, LONG proc, WORD mode );
    LONG reserved[3];
} DEVDRV;
```

Each of the assigned members of this structure should point to a valid routine that provides the named operation on the device. The routine must preserve registers D2-D7 and A2-A7 returning its completion code in D0. No operating system **TRAP**s should be called from within these routines, however, using the vector tables provided in the **kerinfo** structure returned from the **Dcntl()** call, **GEMDOS** and **BIOS** calls may be used. The specific function that each routine is responsible for is as follows:

Member	Meaning
open	This routine is called by the MiNT kernel after a FILEPTR structure has been created for a file
•	determined to be associated with the device. The routine should perform whatever initialization
	is necessary and exit with a standard GEMDOS completion code.
	This routine is responsible for validating the sharing mode and other file flags to verify that the file
	may be legally opened and should respond with an appropriate error code if necessary.
write	This routine should write <i>bytes</i> number of BYTE s from <i>buf</i> to the file specified in FILEPTR . If the
	file pointer has the O_APPEND bit set, the kernel will perform an <i>lseek()</i> call to the end of the file
	prior to calling this function. If the <code>lseek()/write()</code> series of calls does not guarantee that data will
	be written at the end of a file associated with your device, this function must ensure that the data specified is actually written at the end of the file.
	This function should return with a standard GEMDOS error code or the actual number of BYTE s
	written to the file when complete.
read	This routine should read <i>bytes</i> number of BYTE s from the file specified in FILEPTR and place
	them in the buffer <i>buf</i> . This function should return with a standard GEMDOS error code or the
, .	actual number of bytes read by the routine.
lseek	This routine should move the file position pointer to the appropriate location in the file as
	specified by the parameter <i>where</i> in relation to the seek mode <i>whence</i> . Seek modes are the
	same as with Fseek() . The routine should return a GEMDOS error code or the absolute new position from the start of the file if successful.
ioctl	This routine is called from the system's perspective as Fcntl() and is used to perform file
10011	system/device specific functions. At the very least, your device should support FIONREAD ,
	FIONWRITE, and the file/record locking modes of Fcntl(). The <i>arg</i> parameter of Fcntl() is
	passed as buf.
datime	This routine is used to read or modify the date/time attributes of a file. <i>timeptr</i> is a pointer to two
aatiiiio	LONGs containing the time and date of the file respectively. These LONGs should be used to
	set the file date and time if <i>rwflag</i> is non-zero or filled in with the file's creation date and time if <i>rwflag</i> is 0.
	This function should return with a standard GEMDOS error code or E_OK (0) if successful.
close	This routine is used by the kernel to close an open file. Be aware that if <i>f->links</i> is non-zero,
01000	additional processes still have valid handles to the file. If <i>f->links</i> is 0 then the file is really being
	closed. <i>pid</i> specifies the process closing the file and may not necessarily be the same as the
	process that opened it.
	Device drivers should set the O_LOCK bit on f->flag when the F_SETLKW ioctl()
	call is made. This bit can be tested for when a file is closed and all locks on all files associated
	with the same physical file owned by process <i>pid</i> should be removed. If the file did not have any
	locks created on it by process <i>pid</i> , then no locks should be removed.
	This routine should return with a standard GEMDOS error code or E_OK (0) if successful.
select	This routine is called when a call to Fselect() names a file handled by this device. If <i>mode</i> is
	O_RDONLY then the select is for reading, otherwise, if <i>mode</i> is O_WRONLY then it is for
	writing. If the user Fselect() 's for both reading and writing then two calls to this function will be
	made.
	The routine should return 1L if the device is ready for reading or writing (as appropriate) or it
	should return 0L and arrange to 'wake up' process proc when I/O becomes possible. This is
	usually accomplished by calling the <i>wakeselect()</i> member function of the kernel structure. Note
	that the value in <i>proc</i> is not the same as a PID and is actually a pointer to a PROC structure
	private to the MiNT kernel.
	This routine is called when a device waiting for I/O should no longer be waited for. The mode and

proc parameters are the same as with **select()**. As with **select()**, if neither reading nor writing is to be waited for, two calls to this function will be made.

This routine should return a standard **GEMDOS** error code or **E_OK** (0) if successful.

The **FILEPTR** structure pointed to by a parameter of each of the above calls is defined as follows:

```
typedef struct fileptr
{
     WORD links;
     UWORD flags;
     LONG pos;
     LONG devinfo;
     fcookie fc;
     struct devdrv *dev;
     struct fileptr *next;
}
```

The members of **FILEPTR** have significance as follows:

Member	Meaning			
links	This member contai existence.	ns a value	e indicating the number of copies of this file descriptor currently in	
flags	This member contains a bit mask which indicates several attributes (logically OR'ed together) of the file as follows:			
	Name	Mask	Meaning	
	O_RDONLY	0x0000	File is read-only.	
	O_WRONLY	0x0001	File is write-only.	
	O_RDWR	0x0002	File may be read or written.	
	O_EXEC	0x0003	File was opened to be executed.	
	O_APPEND	8000x0	Writes start at the end of the file.	
	O_COMPAT	0x0000	File-sharing compatibility mode.	
	O_DENYRW	0x0010	Deny read and write access.	
	O_DENYW	0x0020	Deny write access.	
	O_DENYR 0x0030 Deny read access. O_DENYNONE 0x0040 Allow reads and writes.			
	O_NOINHERIT	0x0080	Children cannot use this file.	
	O_NDELAY	0x0100	Device should not block for I/O on this file.	
	O_CREAT	0x0200	File should be created if it doesn't exist.	
	O_TRUNC	0x0400	File should be truncated to 0 BYTE s if it already exists.	
	O_EXCL	0x0800	,	
	O_TTY	0x2000	File is a terminal.	
	O_HEAD	0x4000	File is a pseudo-terminal "master."	
	O_LOCK		File has been locked.	
pos	This field is initialized to 0 when a file is created and should be used by the device driver to store			
	the file position pointer.			
devinfo	This field is reserved for use between the file system and the device driver and may be used as			
		ion to this	is if the file is a TTY, in which case devinfo must be a pointer to a	
,	tty structure.			
fc	This is the file cooki	e for the fi	le as follows:	
	typedef struct	f_cool	ĸie	

```
{
                       FILESYS
                                     *fs;
                       UWORD
                                     dev;
                       UWORD
                                     aux;
                       LONG
                                     index;
            } fcookie;
            fs is a pointer to the file system structure responsible for this device. dev is a UWORD giving a
            useful device ID (such as the Rwabs() device number). The meaning of aux is file system
            dependent. index should be used by file systems to provide a unique means of identifying a file.
            This is a pointer to the DEVDRV structure of the device driver responsible for this file.
dev
            This pointer may be used by device drivers to link copies of duplicate file descriptors to
next
            implement file locking or sharing code.
```

Upon successful return from the **Dcntl()** call, a pointer to a **kerinfo** structure will be returned. The **kerinfo** structure is defined below:

```
typedef LONG (*Func)();
struct kerinfo
       WORD
                 maj version;
       WORD
                 min_version;
       UWORD
                 default mode;
       WORD
                 reserved1;
       Func
                 *bios_tab;
       Func
                  *dos tab;
       VOID
                  (*drvchng)( UWORD dev );
       CLON
                  (*trace)( char *, ... );
                  (*debug)( char *, ... );
       VOID
       VOID
                  (*alert)( char *, ... );
       VOID
                  (*fatal)( char *, ... );
       VOIDP
                  (*kmalloc)( LONG size );
                  (*kfree)( VOIDP memptr );
       ULON
                  (*umalloc)( LONG size );
       VOIDP
                  (*ufree)( LONG memptr );
       VOID
       WORD
                  (*strnicmp)( char *str1, char *str2, WORD maxsrch );
       WORD
                  (*stricmp)( char *str1, char *str2 );
       char *
                  (*strlwr)( char *str );
                  (*strupr)( char *str );
       char *
       WORD
                  (*sprintf)( char *strbuf, const char *fmtstr, ... );
                  (*millis time)( ULONG ms, WORD *td );
       VOID
       LONG
                  (*unixtim)( UWORD time, UWORD date );
                  (*dostim)( LONG unixtime );
       LONG
       VOID
                  (*nap)( UWORD n );
       VOID
                  (*sleep)( WORD que, WORD cond );
       VOID
                  (*wake)( WORD que, WORD cond );
       VOID
                  (*wakeselect)( LONG proc );
       WORD
                  (*denyshare)( FILEPTR *list, FILEPTR *f );
       LOCK *
                  (*denylock)( LOCK *list, LOCK *new );
```

LONG res2[9];

};

The members of the **kerinfo** structure are defined as follows:

calling Getmpb() and is the only safe way from within a device driver or file system. dos_tab This is a pointer to the GEMDOS function jump table. Calling dos_tab[0x3D]() is equivale to calling Fopen() and is the only safe way from within a device driver or file system. drvchng This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. This function is used to send information messages to the kernel for debugging purposes. debug This function is used to send error messages to the kernel for debugging purposes. This function is used to send serious error messages to the kernel for debugging purposes. In it is function is used to send fatal error messages to the kernel for debugging purposes. In it is function is used to send fatal error messages to the kernel for debugging purposes. In it is function is used to send fatal error messages to the kernel for debugging purposes. In it is function is used to send fatal error messages to the kernel for debugging purposes. In it is function is used to send fatal error messages to the kernel for debugging purposes. In it is function is used to send fatal error messages to the kernel for debugging purposes. In it is function to allocate memory. In it is function to allocate memory allocated with memory management function to allocate memory and attach it to the current process. The memory will be released automatically when the current process exiting used to send fatal error messages to the kernel for debugging purposes. In it is function to allocate memory and attach it to the current process. The memory management function to allocate memory and attach it to the current process. The memory management function to allocate memory and attach it to the current process. The memory management function to allocate memory and attach it to the string in the function to allocate memory and attach it to the string in the function to allocate memory	Member	Meaning
min_version This WORD contains the minor kernel version number. default_mode reserved1 This UWORD contains the default access permissions for a file. reserved1 Reserved. bios_tab This is a pointer to the BIOS function jump table. Calling bios_tab[0x00]() is equivalent to calling Getmpb() and is the only safe way from within a device driver or file system. dos_tab This is a pointer to the GEMDOS function jump table. Calling dos_tab[0x3D]() is equivale to calling Fopen() and is the only safe way from within a device driver or file system. drvchng This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. trace This function is used to send information messages to the kernel for debugging purposes. debug This function is used to send error messages to the kernel for debugging purposes. alert This function is used to send fatal error messages to the kernel for debugging purposes. kmalloc Use this internal heap memory management function to allocate memory. kfree Use this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exiture ufree Use this internal heap memory management function to allocate memory allocated with ufree(). stricmp	maj_version	This WORD contains the kernel version number.
reserved1 Reserved. bios_tab This is a pointer to the BIOS function jump table. Calling bios_tab[0x00]() is equivalent to calling Getmpb() and is the only safe way from within a device driver or file system. dos_tab This is a pointer to the GEMDOS function jump table. Calling dos_tab[0x3D]() is equivale to calling Fopen() and is the only safe way from within a device driver or file system. drvchng This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. This function is used to send information messages to the kernel for debugging purposes debug debug This function is used to send error messages to the kernel for debugging purposes. alert This function is used to send serious error messages to the kernel for debugging purposes. kmalloc Use this internal heap memory management function to allocate memory. kfree Use this internal heap memory management function to allocate memory and attach it to to current process. The memory will be released automatically when the current process exiture. ufree Use this internal heap memory management function to allocate memory and attach it to to current process. The memory will be released automatically when the current process exiture. stricmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal.		This WORD contains the minor kernel version number.
This is a pointer to the BIOS function jump table. Calling bios_tab[0x00]() is equivalent to calling Getmpb() and is the only safe way from within a device driver or file system. This is a pointer to the GEMDOS function jump table. Calling dos_tab[0x3D]() is equivale to calling Fopen() and is the only safe way from within a device driver or file system. This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. This function is used to send information messages to the kernel for debugging purposes debug This function is used to send error messages to the kernel for debugging purposes. In this function is used to send serious error messages to the kernel for debugging purposes. In this function is used to send fatal error messages to the kernel for debugging purposes. In this function is used to send fatal error messages to the kernel for debugging purposes. In this function is used to send fatal error messages to the kernel for debugging purposes. In this function is used to send fatal error messages to the kernel for debugging purposes. In this function is used to send fatal error messages to the kernel for debugging purposes. In this function is used to send fatal error messages to the kernel for debugging purposes. In this function to it is used to send fatal error messages to the kernel for debugging purposes. In this function to it is used to send fatal error messages to the kernel for debugging purposes. In this function to it is used to send fatal error messages to the kernel for debugging purposes. In this function to it is used to send fatal error messages to the kernel for debugging purposes. In this function to it is used to send fatal error messages to the kernel for debugging purpose that it to to use the send of the kernel for debugging purpose that it to to use the memory and attach it to the use the function to allocate memory. In this function converts all alphabe	default_mode	This UWORD contains the default access permissions for a file.
calling Getmpb() and is the only safe way from within a device driver or file system. dos_tab This is a pointer to the GEMDOS function jump table. Calling dos_tab[0x3D]() is equivale to calling Fopen() and is the only safe way from within a device driver or file system. drvchng This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. trace This function is used to send information messages to the kernel for debugging purposes debug This function is used to send error messages to the kernel for debugging purposes. alert This function is used to send serious error messages to the kernel for debugging purposes. kralloc Use this internal heap memory management function to allocate memory. kfree Use this internal heap memory management function to allocate memory and attach it to the current process. The memory will be released automatically when the current process exity ufree Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. Sprintf This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case.	reserved1	Reserved.
This is a pointer to the GEMDOS function jump table. Calling dos_tab[0x3D]() is equivale to calling Fopen() and is the only safe way from within a device driver or file system. This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. This function is used to send information messages to the kernel for debugging purposes debug. This function is used to send error messages to the kernel for debugging purposes. In it function is used to send serious error messages to the kernel for debugging purposes. It is function is used to send fatal error messages to the kernel for debugging purposes. In it function is used to send fatal error messages to the kernel for debugging purposes. It is the this internal heap memory management function to allocate memory. In this function is used to send fatal error messages to the kernel for debugging purposes. It is the this internal heap memory management function to allocate memory. In this function is used to send fatal error messages to the kernel for debugging purposes. It is the this internal heap memory management function to allocate memory. In this function is used to send fatal error messages to the kernel for debugging purposes. It is the thin the thin this internal heap memory management function to allocate memory allocated with the function. In this function the parameter memory management function to allocate memory and attach it to the current process. The memory will be released automatically when the current process exity function. In this function compares maxsich characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. In this function converts all alphabetic characters in str to lower case. In this function converts all alphabetic characters in str to lower case. In this function converts all alphabetic characters in str to upper ca	bios_tab	This is a pointer to the BIOS function jump table. Calling bios_tab[0x00]() is equivalent to
to calling Fopen() and is the only safe way from within a device driver or file system. drvchng This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. trace This function is used to send information messages to the kernel for debugging purposes debug This function is used to send error messages to the kernel for debugging purposes. This function is used to send serious error messages to the kernel for debugging purposes. In function is used to send fatal error messages to the kernel for debugging purposes. In function is used to send fatal error messages to the kernel for debugging purposes. In function is used to send fatal error messages to the kernel for debugging purposes. In function is used to send fatal error messages to the kernel for debugging purposes. In function is used to send fatal error messages to the kernel for debugging purposes. In function to use this internal heap memory management function to allocate memory. In function to use this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exity for the use this internal heap memory management function to allocate memory allocated with fur fur function. In function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. In function converts all alphabetic characters in str to lower case. In function converts all alphabetic characters in str to lower case. In function is the same as the 'C' library sprintf() function except that it will only convert sprintf This function converts the millisecond time value in ms to a GEMDOS time in to[0] and do in to[1]. In function converts a GEMDOS time and date in a UNIX format LONG. This function converts a UNIX format LONG time/date value into a GEMDOS		
This function should be called by a device driver if a media change was detected on the device during an operation. The parameter dev is the BIOS device number of the device. This function is used to send information messages to the kernel for debugging purposes. This function is used to send error messages to the kernel for debugging purposes. This function is used to send serious error messages to the kernel for debugging purpose. This function is used to send serious error messages to the kernel for debugging purpose. This function is used to send fatal error messages to the kernel for debugging purposes. It is function is used to send fatal error messages to the kernel for debugging purposes. It is function to send fatal error messages to the kernel for debugging purposes. It is the kernel for debugging purposes. It is function to send fatal error messages to the kernel for debugging purposes. It is function to send fatal error messages to the kernel for debugging purposes. It is the kernel for debugging purposes. It is send for debugging purposes. It is send fatal error messages to the kernel for debugging purposes were debugging purposes. It is send fatal error messages to the kernel for debugging purposes were memory allocated with fatal error messages to the kernel for debugging purposes. It is send fatal error messages to the kernel for debugging purposes the memory allocated memory allocated with fatal error messages to the kernel for debugging purposes. It is to termel for debugging purposes the memory allocated with fatal error messages to the kernel for debugging purposes. It is to debugging purposes the kernel for debugging purposes to the kernel for debugging purposes. It is allocate memory allocated with fatal error messages to the kernel for debugging purposes. It is to the kernel for debugging purposes. It is to the ker	dos_tab	
device during an operation. The parameter dev is the BIOS device number of the device. trace This function is used to send information messages to the kernel for debugging purposes. debug This function is used to send error messages to the kernel for debugging purposes. alert This function is used to send serious error messages to the kernel for debugging purposes. This function is used to send fatal error messages to the kernel for debugging purposes. kmalloc Use this internal heap memory management function to allocate memory. kfree Use this internal heap memory management function to free memory allocated with kmalloc(). umalloc Use this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exitinge Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strivpr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. Sprintf This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in str to upper case. This function converts all alphabetic characters in		
trace This function is used to send information messages to the kernel for debugging purposes debug This function is used to send error messages to the kernel for debugging purposes. It along This function is used to send serious error messages to the kernel for debugging purposes. It is function is used to send fatal error messages to the kernel for debugging purposes. It is function is used to send fatal error messages to the kernel for debugging purposes. It is function is used to send fatal error messages to the kernel for debugging purposes. It is function to send fatal error messages to the kernel for debugging purposes. It is function to allocate memory. It is function to allocate memory. It is this internal heap memory management function to allocate memory and attach it to the current process. The memory will be released automatically when the current process exity. It is function to allocate memory allocated with send function to allocate memory allocated with send function. It is function to allocate memory and attach it to the current process. The memory will be released automatically when the current process exity. It is function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. It is function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. It is function converts all alphabetic characters in str to lower case. It is function converts all alphabetic characters in str to upper case. It is function converts all alphabetic characters in str to upper case. It is function converts all alphabetic characters in str to upper case. It is function converts the millisecond time value in ms to a GEMDOS time in ta[0] and date in ta[1]. It is function converts a GEMDOS time and date in a UNIX format LONG.	drvchng	
debugThis function is used to send error messages to the kernel for debugging purposes.alertThis function is used to send serious error messages to the kernel for debugging purposes.fatalThis function is used to send fatal error messages to the kernel for debugging purposes.kmallocUse this internal heap memory management function to allocate memory.kfreeUse this internal heap memory management function to free memory allocated with kmalloc().umallocUse this internal heap memory management function to allocate memory and attach it to a current process. The memory will be released automatically when the current process exitoreufreeUse this internal heap memory management function to allocate memory allocated with ufree().strnicmpThis function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal.stricmpThis function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal.striwrThis function converts all alphabetic characters in str to lower case.struprThis function converts all alphabetic characters in str to upper case.sprintfThis function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H).millis_timeThis function converts the millisecond time value in ms to a GEMDOS time in ta[0] and datin ta[1].unixtimThis function converts a GEMDOS time and date in a UNIX format LONG.dostimThis function converts a UNIX f		
alertThis function is used to send serious error messages to the kernel for debugging purposes.fatalThis function is used to send fatal error messages to the kernel for debugging purposes.kmallocUse this internal heap memory management function to allocate memory.kfreeUse this internal heap memory management function to free memory allocated with kmalloc().umallocUse this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exitufreeUse this internal heap memory management function to allocate memory allocated with ufree().strnicmpThis function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal.stricmpThis function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is higher than str2, or 0 if they are equal.striwrThis function converts all alphabetic characters in str to lower case.struprThis function converts all alphabetic characters in str to upper case.sprintfThis function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H).millis_timeThis function converts the millisecond time value in ms to a GEMDOS time in ta[0] and da in ta[1].unixtimThis function converts a UNIX format LONG time/date value into a GEMDOS time/date	trace	
fatal This function is used to send fatal error messages to the kernel for debugging purposes. kmalloc Use this internal heap memory management function to allocate memory. kfree Use this internal heap memory management function to free memory allocated with kmalloc(). umalloc Use this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exit ufree Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. striwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and da in ta[1]. unixtim This function converts a UNIX format LONG time/date value into a G	debug	
kmalloc Use this internal heap memory management function to allocate memory. kfree Use this internal heap memory management function to free memory allocated with kmalloc(). umalloc Use this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exitofree ufree Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in to[0] and do in to[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into	alert	
kfree Use this internal heap memory management function to free memory allocated with kmalloc(). umalloc Use this internal heap memory management function to allocate memory and attach it to current process. The memory will be released automatically when the current process exitories and returns a negative value if str1 to str2 and returns a negative value if str1 is higher than str2, or 0 if they are equal. strium This function converts all alphabetic characters in str to lower case. str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf (function except that it will only convert sprintf) function except that it will only convert sprintf (function except that it will only convert sprintf).	fatal	This function is used to send fatal error messages to the kernel for debugging purposes.
kmalloc(). umalloc Use this internal heap memory management function to allocate memory and attach it to a current process. The memory will be released automatically when the current process exiture ufree Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and date in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	kmalloc	, ,
current process. The memory will be released automatically when the current process exitufree Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and da in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. This function converts a UNIX format LONG time/date value into a GEMDOS time/date	kfree	
ufree Use this internal heap memory management function to allocate memory allocated with ufree(). strnicmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and date in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	umalloc	Use this internal heap memory management function to allocate memory and attach it to the
tricmp This function compares maxsrch characters of str1 to str2 and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. Stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. Strlwr This function converts all alphabetic characters in str to lower case. Strupr This function converts all alphabetic characters in str to upper case. Sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and datin ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. This function converts a UNIX format LONG time/date value into a GEMDOS time/date		current process. The memory will be released automatically when the current process exits.
str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. stricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and date in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	ufree	· · · · · · · · · · · · · · · · · · ·
tricmp This function compares two NULL terminated strings, str1 to str2, and returns a negative value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. Strlwr This function converts all alphabetic characters in str to lower case. Strupr This function converts all alphabetic characters in str to upper case. This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). This function converts the millisecond time value in ms to a GEMDOS time in to[0] and da in to[1]. Unixtim This function converts a GEMDOS time and date in a UNIX format LONG. This function converts a UNIX format LONG time/date value into a GEMDOS time/date	strnicmp	This function compares maxsrch characters of str1 to str2 and returns a negative value if
value if str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal. strlwr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in td[0] and da in td[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date		str1 is lower than str2, a positive value if str1 is higher than str2, or 0 if they are equal.
equal. strivr This function converts all alphabetic characters in str to lower case. strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in to[0] and da in to[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	stricmp	This function compares two NULL terminated strings, <i>str1</i> to <i>str2</i> , and returns a negative
strupr This function converts all alphabetic characters in str to upper case. sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in td[0] and da in td[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date		, ,
sprintf This function is the same as the 'C' library sprintf() function except that it will only convert SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in td[0] and da in td[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	strlwr	This function converts all alphabetic characters in <i>str</i> to lower case.
SPRINTF_MAX characters (defined in TOSDEFS.H). millis_time This function converts the millisecond time value in ms to a GEMDOS time in ta[0] and data in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG. dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	strupr	This function converts all alphabetic characters in <i>str</i> to upper case.
in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG . dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	sprintf	
in ta[1]. unixtim This function converts a GEMDOS time and date in a UNIX format LONG . dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	millis_time	This function converts the millisecond time value in <i>ms</i> to a GEMDOS time in <i>td</i> [0] and date
dostim This function converts a UNIX format LONG time/date value into a GEMDOS time/date	_	
	unixtim	This function converts a GEMDOS time and date in a UNIX format LONG .
value. The return value contains the time in the upper WORD and the date in the lower	dostim	This function converts a UNIX format LONG time/date value into a GEMDOS time/date
		value. The return value contains the time in the upper WORD and the date in the lower
WORD.		WORD.
nap This function causes a delay of <i>n</i> milliseconds.	nap	This function causes a delay of <i>n</i> milliseconds.
sleep This function causes the current process to sleep, placing it on the system que que until	sleep	This function causes the current process to sleep, placing it on the system que que until
condition <i>cond</i> is met.		condition cond is met.
wake This function causes all processes in que que, waiting for condition cond, to be woken.	wake	This function causes all processes in que que, waiting for condition cond, to be woken.
wakeselect This function wakes a process named by the code proc currently doing a select operation	wakeselect	This function wakes a process named by the code proc currently doing a select operation.
denyshare This function determines whether the sharing mode of <i>f</i> conflicts with any of the files given the linked list <i>list</i> .	denyshare	This function determines whether the sharing mode of <i>f</i> conflicts with any of the files given in the linked list <i>list</i> .
denylock This function determines whether a new lock new conflicts with any existing lock in the	denylock	This function determines whether a new lock <i>new</i> conflicts with any existing lock in the
linked list list. The LOCK structure is used internally by the kernel and is defined as follow		linked list list. The LOCK structure is used internally by the kernel and is defined as follows:

Loadable File Systems

MiNT supports loadable file systems to provide support for those other than **TOS** (such as POSIX, HPFS, ISO 9660 CD-ROM, etc.) The **MiNT** kernel will automatically load file system '.XFS' executables found in the \MULTITOS or root directory. As of **MiNT** version 1.08, it is also possible to have a TSR program install a file system with the **Dcntl**() call.

When the file system is executed by **MiNT** (i.e. not via **Dcntl**()), **MiNT** creates an 8K stack and shrinks the TPA so a call to **Mshrink**() is not necessary. The first instruction of the code segment of the file is JSR'ed to with a pointer to a **kerinfo** (as defined above) structure at 4(sp). The file system should use this entry point to ensure that it is running on the minimum version of **MiNT** needed and that any other aspects of the system are what is required for the file system to operate.

It is not necessary to scan existing drives to determine if they are compatible with the file system as that is accomplished with the file system root() function (defined below). If the file system needs to make **MiNT** aware of drives that would not be automatically recognized by the system, it should update the longword variable $_drvbits$ at location 0x04F2 appropriately.

If the file system was unable to initialize itself or the host system is incapable of supporting it, the entry stub should return with a value of 0L in d0. If the file system installs successfully, it should return a pointer to a **FILESYS** (defined below) structure in d0. A file system should never call **Pterm()** or **Ptermres(**).

All file system functions, including the entry stub, must preserve registers d2-d7 and a2-a7. Any return values should be returned in d0. Function arguments are passed on the stack. The following listing defines the **FILESYS** structure:

```
LONG
                          (*getxattr)( fcookie *file, XATTR *xattr );
       LONG
                          (*chattr)( fcookie *file, WORD attr );
                          (*chown)( fcookie *file, WORD uid, WORD gid );
       LONG
       LONG
                          (*chmode)( fcookie *file, WORD mode );
                          (*mkdir)( fcookie *dir, char *name, UWORD mode );
       LONG
       LONG
                          (*rmdir)( fcookie *dir, char *name );
       LONG
                          (*remove)( fcookie *dir, char *name );
       LONG
                          (*getname)( fcookie *relto, fcookie *dir, char *pathname
       );
       LONG
                          (*rename)( fcookie *olddir, fcookie *oldname,
                                       fcookie *newdir, fcookie *newname );
       LONG
                          (*opendir)( DIR *dirh, WORD tosflag );
       LONG
                          (*readdir)( DIR *dirh, char *name, WORD namelen,
                                       fcookie *fc );
       LONG
                          (*rewinddir)( DIR *dirh );
       LONG
                          (*closedir)( DIR *dirh );
       LONG
                          (*pathconf)( fcookie *dir, WORD which );
       LONG
                          (*dfree)( fcookie *dir, long *buf );
       LONG
                          (*writelabel)( fcookie *dir, char *name );
       LONG
                          (*readlabel)( fcookie *dir, char *name );
       LONG
                          (*symlink)( fcookie *dir, char *name, char *to );
       LONG
                          (*readlink)( fcookie *file, char *buf, short buflen );
                          (*hardlink)( fcookie *fromdir, char *fromname,
       LONG
                                       fcookie *todir, char *toname );
       LONG
                          (*fscntl)( fcookie *dir, char *name, WORD cmd, LONG arg
       );
       LONG
                          (*dskchng)( WORD dev );
       LONG
                          zero;
} FILESYS;
```

The members of the **FILESYS** structure are interpreted by **MiNT** as follows:

Member	Meaning		
next	This member is a pointer left as NULL .	to the ne	xt FILESYS structure in the kernel's linked list. It should be
fsflags	This is a bit mask of flags	which de	efine attributes of the file system as follows:
	Name	Mask	Meaning
	FS_KNOPARSE	0x01	Kernel shouldn't do directory parsing (common for networked file systems).
	FS_CASESENSITIVE	0x02	File system names are case-sensitive (common for Unix compatible file systems).
	FS_NOXBIT	0x04	Files capable of being read are capable of being executed (present in most file systems).
root	associated with BIOS de turn, to determine which f recognizes the drive spec	evice <i>dev</i> . ile system cified by a is not con	el to retrieve a file cookie for the root directory of the drive When initializing, the kernel will query each file system, in a should handle a particular drive. If your file system dev it should fill in the fcookie structure as appropriate and appropriate with your file system, return an appropriate negative RIVE).

lookup	not set, name FS_KNOPA If the file is fo	e will be the r RSE bit was und, the fcoo	late a file name into a cookie. If the FS_KNOPARSE bit of <i>fsflags</i> is name of a file in the directory specified by the fcookie <i>dir</i> . If the set, <i>name</i> will be a path name relative to the specified directory <i>dir</i> . okie structure <i>fc</i> should be filled in with appropriate details and either <i>me</i> is '' and <i>dir</i> specifies the root directory) should be returned,	
			error code (like EFILNF) should be returned.	
			,	
			L name or with a name of '.' should always succeed and return a urrent directory. When creating a file cookie, symbolic links should	
	never be follo	owed.		
creat			he kernel to instruct the file system to create a file named <i>name</i> in the with <i>attrib</i> attributes (as defined by Fattrib()) and <i>mode</i> permissions	
	Name	<u>Mask</u>	Permission	
	S_IXOTH	0x0001	Execute permission for all others.	
	S_IWOTH	0x0001	Write permission for all others.	
	S_IROTH	0x0002	Read permission for all others.	
	SIXGRP	0x0004	Execute permission for processes with same group ID.	
	S_IWGRP	0x0000	Write permission for processes with same group ID.	
	S_IRGRP	0x0010	Read permission for processes with same group ID.	
	S IXUSR	0x0040	Execute permission for processes with same user ID.	
	S_IWUSR	0x0080	Write permission for processes with same user ID.	
	S_IRUSR 0x0100 Read permission for processes with same user ID. S_ISVTX 0x0200 Unused			
	S ISGID	0x0400	Alter effective group ID when executing this file.	
	S_ISUID 0x0800 Alter effective user ID when executing this file.			
	S_IFCHR 0x2000 File is a BIOS special file.			
	S_IFDIR 0x4000 File is a directory.			
	S_IFREG	0x8000	File is a regular file.	
	S_IFIFO	0xA000	File is a FIFO.	
	S_IMEM	0xC000	File is a memory region.	
	S_IFLNK 0xE000 File is a symbolic link.			
	If the file is created successfully, the fcookie structure fc should be filled in to represent the newly created file and E_OK should be returned. On an error, an appropriate GEMDOS error code should be returned.			
getdev	This function is used by the kernel to identify the device driver that should be used to do file I/O			
3			ne function should return a pointer to the device driver and place a	
		•	ongword pointed to by devspecial. If the function fails, the function	
	should return	and place a	negative GEMDOS error code in the longword pointed to by	
	devspecial.			
getxattr	This function	should fill in t	the XATTR structure pointed to by <i>xattr</i> with the extended attributes of	
	file fc. If the fo	unction succe	eeds, the routine should return E_OK , otherwise a negative GEMDOS	
	error code sh			
chattr	This function	is called by t	he kernel to instruct the file system to change the attributes of file fc to	
	those in attr (low eight bits being signifigant). The function should return a standard exit.	
chown			he kernel to instruct the file system to change the file fc's group and	
SHOWH	user ownersh	nip to <i>gid</i> and	I uid respectively. The kernel checks access permissions prior to file system does not have to.	

This function is called by the kernel to instruct the file system to change the access permissions of file fc to those in mode. The mode parameter passed to this function will never contain anything but access permission information (i.e. no file type information will be contained in mode). The call should return a standard GEMDOS error code on exit. mkdir This function should create a new subdirectory called name in directory dir with access permissions of mode. The file system should ensure that directories such as '.' and '' are created and that a standard GEMDOS error code is returned. mdir This function should remove the directory whose name is name and whose cookie is pointed to by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. remove This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. getname This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned.
anything but access permission information (i.e. no file type information will be contained in mode). The call should return a standard GEMDOS error code on exit. This function should create a new subdirectory called name in directory dir with access permissions of mode. The file system should ensure that directories such as '.' and '' are created and that a standard GEMDOS error code is returned. This function should remove the directory whose name is name and whose cookie is pointed to by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. Temove This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
mode). The call should return a standard GEMDOS error code on exit. This function should create a new subdirectory called name in directory dir with access permissions of mode. The file system should ensure that directories such as '.' and '' are created and that a standard GEMDOS error code is returned. This function should remove the directory whose name is name and whose cookie is pointed to by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. Temove This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
This function should create a new subdirectory called name in directory dir with access permissions of mode. The file system should ensure that directories such as '.' and '' are created and that a standard GEMDOS error code is returned. This function should remove the directory whose name is name and whose cookie is pointed to by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. Temove This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
created and that a standard GEMDOS error code is returned. This function should remove the directory whose name is name and whose cookie is pointed to by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
This function should remove the directory whose name is name and whose cookie is pointed to by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
by dir. This call should allow the removal of symbolic links to directories and return a standard GEMDOS error code. This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
This function should delete the file named name that resides in directory dir. If more than one 'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
'hard' link to this file exists, then only this link should be destroyed and the file contents should be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
be left untouched. Symbolic links to file fc, however, should be removed. This function should not allow the deletion of directories and should return with a standard GEMDOS error code. This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
not allow the deletion of directories and should return with a standard GEMDOS error code. getname This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
This function should fill in the buffer pointed to by pathname with as many as PATH_MAX (128) characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
characters of the path name of directory dir expressed relatively to directory relto. If relto and dir point to the same directory, a NULL string should be returned. For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
point to the same directory, a NULL string should be returned. For example, if <i>relto</i> points to directory "\FOO" and <i>dir</i> points to directory "\FOO\BAR\SUB" then <i>pathname</i> should be filled in with "\BAR\SUB". This function should rename the file <i>oldname</i> which resides in directory <i>olddir</i> to the new name <i>newname</i> which resides in <i>newdir</i> . The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. <i>opendir</i> This function opens directory <i>dirh</i> for reading. The parameter <i>tosflag</i> is a copy of the <i>flags</i>
For example, if relto points to directory "\FOO" and dir points to directory "\FOO\BAR\SUB" then pathname should be filled in with "\BAR\SUB". This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. Opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
then pathname should be filled in with "\BAR\SUB". rename This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
then pathname should be filled in with "\BAR\SUB". rename This function should rename the file oldname which resides in directory olddir to the new name newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
 newname which resides in newdir. The file system may choose to support or not support cross-directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
directory renames. The function should return a standard GEMDOS error code. If no renames at all are supported then EINVFN should be returned. opendir This function opens directory <i>dirh</i> for reading. The parameter <i>tosflag</i> is a copy of the <i>flags</i>
at all are supported then EINVFN should be returned. opendir This function opens directory <i>dirh</i> for reading. The parameter <i>tosflag</i> is a copy of the <i>flags</i>
opendir This function opens directory dirh for reading. The parameter tosflag is a copy of the flags
member of the DIR structure as defined below:
typedef struct dirstruct
{
fcookie fc; /* Directory cookie */
UWORD index; /* Index of current entry */
UWORD flags; /* TOS_SEARCH (1) or 0 */ char fsstuff[60]; /* File system dependent */
} DIR;
If tosflags (dirstruct.flags) is contains the mask TOS_SEARCH the file system is responsible
for parsing the names into something readable by TOS domain applications. The file system
should initialize the index and fsstuff members of dirh and return an appropriate GEMDOS
error code.
readdir This function should read the next filename from directory dirh. The fcookie structure fc should
be filled in with the details of this file. If <i>dirh->flags</i> does not contain the mask TOS_SEARCH
then the filename should be copied into the buffer pointed to by name. If dirh->flags does
contain the mask TOS_SEARCH then the first four bytes of <i>name</i> should be treated as a
longword and filled in with an index value uniquely identifying the file and the filename should be
copied starting at &name[4].
In either case, if the filename is longer than <i>namelen</i> , rather than filling in the buffer <i>name</i> , the
In either case, if the filename is longer than <i>namelen</i> , rather than filling in the buffer <i>name</i> , the function should return with ENAMETOOLONG . If this is the last file in the directory, ENMFIL
In either case, if the filename is longer than <i>namelen</i> , rather than filling in the buffer <i>name</i> , the function should return with ENAMETOOLONG . If this is the last file in the directory, ENMFIL should be returned, otherwise return E_OK .
In either case, if the filename is longer than namelen, rather than filling in the buffer name, the function should return with ENAMETOOLONG. If this is the last file in the directory, ENMFIL should be returned, otherwise return E_OK. rewinddir

pathconf	This function should return information about the directory <i>dir</i> based on mode <i>mode</i> . For <i>mode</i>
	values and return values, see Dpathconf() .
dfree	This function should return free space information about the drive directory <i>dir</i> is located on.
	The format of the buffer pointed to by <i>buf</i> is the same as is used by Dfree() . This function should
	return a standard GEMDOS error code.
writelabel	This function is used to change the volume name of a drive which contains the directory <i>dir</i> . The
	new name <i>name</i> should be used to write (or rename the volume label). If the write is actually an
	attempt to rename the label and the file system does not support this function then EACCDN
	should be returned. If the file system does not support the concept of volume labels then
	EINVFN should be returned. Otherwise, a return value of E_OK is appropriate.
readlabel	This function should copy the volume label name of the drive on which directory <i>dir</i> is contained
	in the buffer name. If namelen is less than the size of the volume name, ENAMETOOLONG
	should be returned. If the concept of volume names is not supported by the file system, EINVFN
	should be returned. If no volume name was ever created, EFILNF should be returned. Upon
	successful error of the call, E_OK should be returned.
symlink	This function should create a symbolic link in directory dir named name. The symbolic link
	should contain the NULL terminated string in <i>to</i> . If the file system does not support symbolic
	links it should return EINVFN , otherwise a standard GEMDOS error code should be returned.
readlink	This function should copy the contents of symbolic link <i>file</i> into buffer <i>buf</i> . If the length of the
	contents of the symbolic link is greater than <i>buflen</i> , ENAMETOOLONG should be returned. If
	the file system does not support symbolic links, EINVFN should be returned. In all other cases,
	a standard GEMDOS error code should be returned.
hardlink	This function should create a 'hard' link called toname residing in todir from the file named
	fromname residing in fromdir. If the file system does not support hard links, EINVFN should be
	returned. Otherwise, a standard GEMDOS error code should be returned.
fscntl	This function performs a file system specific function on a file whose name is <i>name</i> that resides
	in directory dir. The cmd and arg functions parallel those of Dcntl() . In most cases, this function
	should simply return EINVFN . If your file system wishes to expose special features to the user
	through Dcntrl() then your file system should handle them here as it sees fit.
dskchng	This function is used by the kernel to confirm a 'media change' state reported by Mediach() . If
	the file system agrees that a media change has taken place, it should invalidate any
	appropriate buffers, free any allocated memory associated with the device, and return 1. The
	kernel will then invalidate any open files and relog the drive with the root() functions of each
	installed file system.
	If a media change has not taken place, simply return a value of 0.
zero	This member is reserved for future expansion and must be set to 0L.

MiNT Interprocess Communication

Pipelines

A pipeline is a special file used for data communication in which the data being read or written is kept in memory. Pipes are created by **Fcreate()**'ing a file in the special directory 'U:\PIPE'. A process which initially opens a pipe is considered the 'server.' Processes writing to or reading from the open pipe are called 'clients.' Both servers and clients may read to and write from the pipe.

Fcreate()'s attr byte takes on a special meaning with pipes as follows:

Name	Bit	Meaning
FA_UNIDIR	0x01	If this bit is set, the pipe will be unidirectional (the server can only write, the client can only read).
FA_SOFTPIPE	0x02	Setting this bit causes reads when no one is writing to return EOF and writes when no one is reading to raise the signal SIGPIPE .
FA_TTY	0x04	Setting this bit will make the pipe a pseudo-TTY, i.e. any characters written by the server will be interpreted (CTRL-C will cause a SIGINT signal to be generated to all clients).

Fpipe() can also be used to create pipes quickly with the **MiNT** kernel resolving any name conflicts. A pipe is deleted when all processes that had obtained a handle to it **Fclose()** it.

A single process may serve as both the client and the server if it maintains two handles (one obtained from **Fopen()** and one from **Fcreate()**). In addition, child processes of the server may inherit the file handle, and thus the server end of the pipe.

A special system call, **Salert**(), sends a string to a pipe called 'U:\PIPE\ALERT'. If a handler is present that reads from this pipe, an alert with the text string will be displayed.

Signals

Signals are messages sent to a process that interrupt normal program flow in a way that may be defined by the receiving application. Signals are sent to a process with the function **Pkill()**. The call is named **Pkill()** because the default action for most signals is the termination of the process. If a process expects to receive signals it should use **Psignal()**, **Psigsetmask()**, **Psigblock()**, or **Psigaction()** to modify that behavior by installing a handler routine, ignoring the signal, or blocking the signal completely.

Signal handlers should return by executing a 680x0 RTS instruction or by calling **Psigreturn**(). Current signals sent and recognized by **MiNT** processes are as follows:

Signal	Number	Meaning
SIGNULL	0	This signal is actually a dead signal since it has no effect and is never delivered. Its only purpose is to determine if a child process has exited. A Pkill() call with this signal number will return successfully if the process is still running or fail if not.
SIGHUP	1	This signal indicates that the terminal connected to the process is no longer valid. This signal is sent by window managers to processes when the user has closed your window. The default action for this signal is to kill the process.
SIGINT	2	This signal indicates that the user has interrupted the process with CTRL-C. The default action for this signal is to kill the process.
SIGQUIT	3	This signal is sent when the user presses CTRL-\. The default action for this signal is to kill the process.

SICIL I	4	This signal is sent after a 680x0 Illegal Instruction
SIGILL	4	Exception has occurred. The default action for this
		signal is to kill the process. Catching this signal is
		unrecommended.
SIGTRAP	5	This signal is sent after each instruction is executed
OIO III		when the system is in single-step trace mode.
		Debuggers should catch this signal, other
		processes should not.
SIGABRT	6	This signal is sent when something has gone wrong
		internally and the program should be aborted
		immediately. The default action for this signal is to
		kill the process. It is unrecommended that you catch
		this signal.
SIGPRIV	7	This signal is sent to a process that attempts to
		execute an instruction that may only be executed in
		supervisor mode while in user mode. The default
		action for this signal is to kill the process.
SIGFPE	8	This signal is sent when a division by 0 or floating-
		point exception occurs. The default action for this
21214111		signal is to kill the process.
SIGKILL	9	This signal forcibly kills the process. There is no
OLODI IO	40	way to catch or ignore this signal.
SIGBUS	10	This signal is sent when a 680x0 Bus Error
		Exception occurs. The default action for this signal
SIGSEGV	11	is to kill the process. This signal is sent when a 680x0 Address Error
SIGSEGV	111	Exception occurs. The default action for this signal
		is to kill the process.
SIGSYS	12	This signal is sent when an argument to a system
0.0010	12	call is bad or out of range and the call doesn't have
		a way to report errors. For instance, Super(0L) will
		send this signal when already in supervisor mode.
		The default action for this signal is to kill the
		process.
SIGPIPE	13	This signal is sent when a pipe you were writing to
		has no readers. The default action for this signal is
		to kill the process.
SIGALRM	14	This signal is sent when an alarm sent by Talarm()
		is triggered. The default action for this signal is to
		kill the process.
SIGTERM	15	This signal indicates a 'polite' request for the
		process to cleanup & exit. This signal is sent when
		a process is dragged to the trashcan on the
		desktop. The default action for this signal is to kill
CICCTOR	47	the process.
SIGSTOP	17	This signal is sent to a process to suspend it. It cannot be caught, blocked, or ignored. This signal
		is usually used by debuggers.
SIGTSTP	18	This signal is sent when the user presses CTRL-Z
3101317	10	requesting that the process suspend itself. The
		default action for this signal is to suspend the
		process until a SIGCONT signal is caught.
SIGCONT	19	This signal is sent to restart a process stopped with
3.000,11		SIGSTOP or SIGTSTP. The default action for this
		signal is to resume the process.
	I.	1 digital to to room to procood.

		I —
SIGCHLD	20	This signal is sent when a child process has exited or has been suspended. As a default, this signal causes no action.
SIGTTIN	21	This signal is sent when a process attempts to read from a terminal in a process group other than its own. The default action is to suspend the process.
SIGTTOU	22	This signal is sent when a process attempts to write to a terminal in a process group other than its own. The default action is to suspend the process.
SIGIO	23	This signal is sent to indicate that I/O is possible on a file descriptor. The default action for this signal is to kill the process.
SIGXCPU	24	This signal is sent when the maximum CPU time allocated to a process has been used. This signal will continue to be sent to a process until it exits. The default action for this signal is to kill the process.
SIGXFSZ	25	This signal is sent to a process when it attempts to modify a file in a way that causes it to exceed the processes' maximum file size limit. The default action for this signal is to kill the process.
SIGVTALRM	26	This signal is sent to a process which has exceed its maximum time limit. The default action for this signal is to kill the process.
SIGPROF	27	This signal is sent to a process to indicate that its profiling time has expired. The default action for this signal is to kill the process.
SIGWINCH	28	This signal indicates that the size of the window in which your process was running has changed. If the process cares about window size it can use Fcntl() to obtain the new size. The default action for this signal is to do nothing.
SIGUSR1	29	This signal is one of two user-defined signals. The default action for this signal is to kill the process.
SIGUSR2	30	This signal is one of two user-defined signals. The default action for this signal is to kill the process.

Memory Sharing

With the enforcement of memory protection under **MultiTOS**, the availability of shared memory blocks is important for applications wishing to share blocks of memory. A shared memory block is opened by **Fcreate()**'ing a file in the directory 'U:\SHM'. After that, a memory block allocated with **Malloc()** or **Mxalloc()** may be attached to the file with **Fcntl(** *handle*, *memptr*, **SHMSETBLK)**.

Any process which uses **Fopen**() and **Fcntl**() with a parameter of **SHMGETBLK** can now read that memory as if it were a disk file. After a process obtains the address of a shared memory block with **SHMGETBLK** the memory is guaranteed to be valid until it calls **Mfree**() on that block even if it **Fclose**()'s the original file handle.

Note that the address returned by **Fcntl()** may be different in different processes. Because of this, data in shared memory blocks should not contain absolute pointers.

When a process is finished with a shared memory block, it should **Mfree()** the address returned by the **Fcntl()** call. A shared memory block is also deleted by the **Fdelete()** call if the file is currently unopened by any other processes.

Other Methods of Communication

Psemaphore() can be used to create named flags which can synchronize the behavior of multiple applications (if adhered to). **Pmsg**() is used to send simple messages between two processes.

MiNT Debugging

MiNT allows a processes' TEXT, DATA, and BSS space to be read and written to with standard **GEMDOS** file commands by opening the process on 'U:\PROC\' A file named "TEST" with a **MiNT** identification of 10 could be opened by specifying the name as 'U:\PROC\TEST.10' or 'U:\PROC\.10'. Opening a file to 'U:\PROC\.-1' will open your own process whereas opening a file to 'U:\PROC\.-2' will open your parent process.

Tracing

A process may be setup for tracing in a number of ways. A child process may be started in trace mode by OR'ing 0x8000 with the **Pexec()** mode number in a **Pexec()** call. A process may also trace another process by opening it as described above and using the **Fcntl()** call with a parameter of **PTRACESFLAGS**. Processes may start tracing on themselves if their parent is prepared for it.

When in trace mode, the process being traced halts and generates a **SIGCHLD** signal to its tracer after every instruction (unless this action is modified). The example below shows how to obtain the process ID of the stopped child and the signal that caused the child to stop.

```
(((int)((x) \& 0xFF)==0x7F) \&\& ((int)(((x)>>8)\&0xFF)!=0))
#define WIFSTOPPED(x)
#define WSTOPSIG(x)
                          ((int)(((x)>>8) \& 0xFF))
HandleSignal( LONG signo )
       WORD pid;
       WORD childsignal;
       ULONG r;
       if( signo == SIGCHLD )
             r = Pwait3(0x2, 0L);
             if( WIFSTOPPED( r ) )
                     pid = r >> 16;
                     childsignal = WSTOPSIG( r );
             }
       }
}
```

After reception of this signal, the child process may be restarted with **Fcntl()** using either the **PTRACEFLOW**, or **PTRACESTEP** commands. Setting **PTRACEFLOW** or

PTRACESTEP causes a **SIGTRAP** signal to be raised on the next program flow change (ex: BRA or JMP) or the instruction respectively.

Modifying the Process Context

A processes' registers may be modified during tracing using the method as illustrated in the following example:

```
struct context
                    regs[15]; // Registers d0-d7, a0-a6
usp; // User stack pointer
sr; // Status register
         LONG
         LONG
         WORD
                    sr;
                                           // Status register
         LONG pc; // Program counter
LONG ssp; // Supervisor stack pointer
LONG tvec; // GEMDOS terminate vector
char fstate[216]; // Internal FPU state
LONG fregs[3*8]; // Registers FPO-FP7
LONG fctrl[3] // Registers FPCR/FPSR/FPIAF
                                            // Registers FPCR/FPSR/FPIAR
         // More undocumented fields exist here
} c;
void
ModifyContext( LONG handle )
         LONG curprocaddr, ctxtsize;
         Fcntl( handle, &curprocaddr, PPROCADDR );
         Fcntl( handle, &ctxtsize, PCTXTSIZE );
         curprocaddr -= 2 * ctxtsize;
         Fseek( curprocaddr, handle, SEEK_SET );
         Fread( handle, (LONG)sizeof(struct context), &c );
         /* Modify context c here */
         Fseek( curprocaddr, handle, SEEK_SET );
         Fwrite( handle, (LONG)sizeof(struct context), &c );
}
```

MiNT Debugging Keys

MiNT may be programmed to output special debugging messages to the debugging device through the use of special system keys. The supported system keys are shown in the table below:

Key Combination	Meaning
CTRL-ALT-F1	Increase the system debugging level by one.
CTRL-ALT-F2	Decrease the system debugging level by one.
CTRL-ALT-F3	Cycle the BIOS output device number used for system debugging messages. This key cycles BIOS devices in the order 1-6-7-8-9-2.
CTRL-ALT-F4	Restore debugging output to the console device.
CTRL-ALT-F5	Output a memory usage map to the debugging device.
CTRL-ALT-F6	Output a list of all system processes to the debugging device.

CTRL-ALT-F7	Toggles debug 'logging' off and on. When debug logging is on, a 50-line buffer is maintained which contains recent debugging messages. Each time a new debugging message is output, the entire 50 line buffer is output as well.
CTRL-ALT-F8	Outputs the 50-line debug log to the debugging device.
CTRL-ALT-F9	Outputs the system memory map to the debugging device. The memory protection flags of each page are shown.
CTRL-ALT-F10	Outputs an extended system memory map to the debugging device. The memory protection status, owner's PID, and format of each memory block are output to the debugging device.

CTRL-ALT-F1 and CTRL-ALT-F2 alter the current system debugging level. **MiNT** supports four debugging levels as follows:

Level	Meaning
0	Only fatal OS errors are reported to the debugging device
	(this is the default mode).
1	Processor exceptions are output to the debugging
	device.
2	Processor exceptions and failed system calls are output
	to the debugging device.
3	Constant MiNT status reports, processor exceptions, and
	failed system calls are output to the debugging device.

The MINT.CNF File

MultiTOS looks for an ASCII text file upon bootup called 'MINT.CNF' which may be used to execute commands or set **MiNT** variables. The following table illustrates what commands are recognized in the 'MINT.CNF' file:

Command	Example	Meaning
cd	cd c:\multitos	Change the GEMDOS
		working directory.
echo	echo "Atari Computer Booting"	Echo a string to the screen.
ren	ren c:\test.prg c:\test.app	Rename a file.
sln	sln c:\level1\level2\level3 u:\deep	Create a symbolic link on
		drive 'U:'.
alias	alias x: u:\proc	Create an alias drive.
exec	exec c:\sam.prg	Execute a program.

The following MiNT variables may be set in the 'MINT.CNF' file:

Variable	Meaning		
INIT	Execute the named TOS program. For example:		
	INIT=c:\multitos\sam.prg		
GEM	Execute the named GEM program. For example:		
	GEM=c:\multitos\miniwin.app		
CON	Redirect console input and output to the named file.		
	For example:		
	CON A desay desay 1		
PRN	CON=u:\dev\modem1 Redirect printer output to the named file. For		
FKN	example:		
	orial pro-		
	PRN=c:\spool.txt		
DEBUG_LEVEL	Set the MiNT debugging level (default is 0). For		
	example:		
	DEBUG LEVEL=1		
DEBUG DEVNO	Set the BIOS device number that MINT will send		
DEBOO_DEVINO	debugging messages to. For example:		
	DEBUG_DEVNO=1		
SLICES	Set the number of 20ms time slices given to an		
	application at a time (the default is 2). For example:		
	SLICES=3		
MAXMEM	Set the maximum amount of memory (in kilobytes)		
	any application can be allocated (the default is		
	unlimited). For example:		
	MAXMEM=8192		
BIOSBUF	Enable/Disable Bconout() optimizations. The		
2.3020.	parameter should be 'Y' to enable or 'N' to disable		
	these optimizations. For example:		
	BIOSBUF=Y		

GEMDOS Character Functions

GEMDOS provides a number of functions to communicate on a character basis with the default system devices. Because of irregularities with these calls in some **TOS** versions, usage of the **BIOS** functions is usually recommended instead (the **BIOS** does not support redirection, however).

The **GEMDOS** character functions are illustrated in the table below:

Device:	Input	Output	Status
con:	Cconin() - Character Cnecin() - No Echo Cconrs() - String	Cconout() - Character Cconws() - String	Cconis() - Input Cconos() - Output
prn:	None	Cprnout()	Cprnos()

aux:	Cauxin()	Cauxout()	Cauxis() - Input
			Cauxos() - Output
N/A	Crawio() and Crawcin()	Crawio()	Cconis() - Input
			Cconos() - Output

GEMDOS Time & Date Functions

GEMDOS provides four functions for the manipulation of time. **Tsetdate()** and **Tsettime()** set the date and time respectively. **Tgetdate()** and **Tgettime()** get the date and time respectively.

As of **TOS** 1.02, the **GEMDOS** time functions also update the **BIOS** time.

GEMDOS Function Calling Procedure

GEMDOS system functions are called via the TRAP #1 exception. Function arguments are pushed onto the current stack in reverse order followed by the function opcode. The calling application is responsible for correctly resetting the stack pointer after the call.

GEMDOS may utilize registers D0-D2 and A0-A2 as scratch registers and their contents should not be depended upon at the completion of a call. In addition, the function opcode placed on the stack will be modified.

The following example for **Super()** illustrates calling **GEMDOS** from assembly language:

'C' compilers often provide a reusable interface to **GEMDOS** that allows new **GEMDOS** calls to be added with a macro as in the following example:

```
#define Super( a ) gemdos( 0x20, a )
```

The gemdos() function used in the above macro can be written in assembly language as follows:

```
.globl
                           _gemdos
              .text
gemdos:
              move.1
                           (sp)+, tlsav
                                            ; Save return address
                                            ; Call GEMDOS
                           #1
              trap
                           t1sav,-(sp)
                                            ; Restore return address
              move.1
              rts
              .bss
t1sav:
                                           ; Return address storage
              പദ 1
                           1
              .end
```

GEMDOS is not guaranteed to be re-entrant and therefore should not be called from an interrupt handler.